

Call Management User's Guide

© Copyright 2008 Infor

All rights reserved. The word and design marks set forth herein are trademarks and/or registered trademarks of Infor and/or its affiliates and subsidiaries. All rights reserved. All other trademarks listed herein are the property of their respective owners.

Important Notices

The material contained in this publication (including any supplementary information) constitutes and contains confidential and proprietary information of Infor.

By gaining access to the attached, you acknowledge and agree that the material (including any modification, translation or adaptation of the material) and all copyright, trade secrets and all other right, title and interest therein, are the sole property of Infor and that you shall not gain right, title or interest in the material (including any modification, translation or adaptation of the material) by virtue of your review thereof other than the non-exclusive right to use the material solely in connection with and the furtherance of your license and use of software made available to your company from Infor pursuant to a separate agreement ("Purpose").

In addition, by accessing the enclosed material, you acknowledge and agree that you are required to maintain such material in strict confidence and that your use of such material is limited to the Purpose described above.

Although Infor has taken due care to ensure that the material included in this publication is accurate and complete, Infor cannot warrant that the information contained in this publication is complete, does not contain typographical or other errors, or will meet your specific requirements. As such, Infor does not assume and hereby disclaims all liability, consequential or otherwise, for any loss or damage to any person or entity which is caused by or relates to errors or omissions in this publication (including any supplementary information), whether such errors or omissions result from negligence, accident or any other cause.

Trademark Acknowledgements

All other company, product, trade or service names referenced may be registered trademarks or trademarks of their respective owners.

Publication Information

Document code	U8954B US
Release	Infor ERP LN 6.1 FP5 Service
Publication date	November 16, 2008

Table of Contents

About this document

Chapter 1 Introduction.....	1-1
Chapter 2 Call Management Concepts.....	2-1
Call handling concepts.....	2-1
Single service concept (SSC).....	2-2
Dual service concept (DSC).....	2-2
Call Handling.....	2-2
Response time.....	2-3
Assign and reassign call.....	2-4
Reassign Call.....	2-4
Diagnostic tree construction.....	2-5
Priorities.....	2-5
Priority Factor.....	2-6
The call's priority factor.....	2-6
Escalated and deferred calls.....	2-7
Escalated calls.....	2-7
Deferred calls.....	2-7
To view escalated calls and deferred calls.....	2-8
To create a physical breakdown from a Bill of Materials.....	2-8
Call Status.....	2-12
Chapter 3 Master Data Setup.....	3-1
To set up Master Data for Call Management.....	3-1
To set up master data.....	3-1
Chapter 4 Call Management Procedures.....	4-1
Call handling.....	4-1
To reassign the call.....	4-2
To transfer the call to Service Order Control.....	4-2

To transfer a call to subcontractor.....	4-3
To transfer a call to Maintenance Sales Order Control.....	4-3
Register call.....	4-3
Transfer call.....	4-5
To transfer a call to Service Order Control.....	4-5
To transfer a call to Maintenance Sales Order Control.....	4-5
To transfer a call to Subcontractor.....	4-6
Solve the call.....	4-6
Call invoicing.....	4-7
Chapter 5 Call Diagnostics.....	5-1
Call diagnostics.....	5-1
Appendix A Glossary.....	A-1
Index	

About this document

Objectives

This document is a User's Guide that is designed to meet the following objectives:

- Master data setup
- Call handling
- Call diagnostics

This document assumes that you already have a general understanding of Infor ERP LN Financials.

Document summary

This document describes the various Call Management processes available, and the procedure to create and process calls.

How to read this document

This document is assembled from online Help topics. As a result, references to other sections in the manual are presented as shown in the following example:

To locate the referred section, refer to the Table of Contents.

Underlined terms indicate a link to a glossary definition. If you view this document online, you can click the underlined text to proceed to the glossary definition of the term.

Customer Support

If you have questions regarding the Infor products described, go to Infor's Customer Support portal at www.infor365.com.

- To access Infor365, go to www.infor365.com and log in. If you do not have an Infor365 account, click **Account Request**, complete the registration form, and a login will be sent to you within 24 hours.
 - To access Infor knowledgebases, documentation, downloads, communities, and incidents, click the appropriate link in the top menu of the home page.
 - To find your local support phone number, click **Contact Infor** in the top right corner of the home page, enter a product name, and click **Search**.
-

Chapter 1

Introduction

1

Call Management (CLM) is the customer's primary link into the service environment. In Call Management, you can register and further handle calls related to products. You can be alerted about existing calls on the selected business partner at the time of registration. The concept of a central call center with several local call centers can be supported taking into account the various time zones. The registered calls can be assigned to any support center or support engineer. When assigned to a specific support engineer, the call enters the individual's queue. Subsequently, the call can be taken up for processing.

Calls can also be assigned to a business partner (subcontractor), for which e-mail is used as a carrier to transfer the call. This e-mail message contains an attachment that contains all relevant call information.

The service organization can agree to specific response times while signing contracts with the customers. Response times could be based on a specific time period or based on specific business days. To honor a possible agreed warranty or contract condition, the call is dispatched to a service center (and service engineer) for field service, to the help desk for support, or to a workshop for depot repair through an RMA order.

The status of the call provides insight into what is done so far and what can be expected further. The status can have values such as Registered and Assigned. Each call has a response time that is controlled.

Calls can escalate if they are not solved within the agreed time frame. In addition, logging what is done and by whom is carried out automatically. This feature enables you to trace and track calls from the start until the end.

This chapter provides a brief description of the concepts of the Call Management module.

Call handling concepts

You can use Call Management to carry out the entire call handling process, which includes:

- Call receipt
- Call logging
- Call dispatching
- Call diagnosis
- Call solving
- Call Invoicing
- Supervisor / unblocking

Service enables either a single service concept (SSC) or a dual service concept (DSC) for the service organization.

Before you can work with the Call Management modules, you must first define the following information:

Prerequisites:

- Configurations (in CFG)
- Items used (in MDM)
- Service organization (in MDM)

You must then set the parameters in the Master Data - Call Management Business Object, as described in Chapter 3.

Single service concept (SSC)

In a single service concept, the process consists of the following steps:

1. Enter call details.
2. Process the call.
3. Start the call timer. This enforces time limits to the solution of the call.
4. Use diagnostics to establish the problem.
5. Enter problem and solution details.
6. Invoice the business partner.

Dual service concept (DSC)

In a dual service concept, the process consists of the following steps. Note that the helpdesk performs Steps 1 and 2, and the assignee performs Steps 3 and onwards.

1. Enter the call details.
2. Assign the call to the relevant service center or support engineer.
3. Reassign the call, if wrongly assigned.
4. Process the call.
5. Start the call timer, which enforces time limits to the solution of the call.
6. Use diagnostics to establish the problem.
7. Enter problem and solution details.
8. Invoice the business partner.

Call Handling

Calls are handled on a time-based priority scheme. The coordination between demand and the processing of calls (problems) takes place through the escalation procedure. ERP LN enables you to monitor the status of calls easily, which also enables you to make early decisions on whether extra or special support is required to solve a problem.

The Call Handling sessions are used from the initial entry of call details until the business partner accepts the problem solution.

The call handling process utilizes data entered in the Master Data sessions throughout the life of a problem call.

The efficiency of call handling is a critical success factor for service organizations. When call handling takes place, issues that influence the efficiency include:

- The time taken to enter the call details, and the ability to view previous calls.
-

- The experience of the support engineers in analyzing the problem, whether as individuals, or as provided by a diagnostic tree of questions and their expected answers.
- The ease of monitoring the call handling process, with an associated escalation procedure if the problem is not solved quickly enough.

Response time

Response times are used to calculate the initial and actual priorities of a call and planned dates.

You can link response times to terms and coverage terms of the following

- Service contracts
- Service contract templates
- Service contract quotations
- Warranties
- Service order activities
- Call parameters
- Business partners

The response time is the maximum elapsed time between the registration of the call and the response. Response times cannot be registered manually. To determine what response time is used, ERP LN considers the service contracts, the general information for this specific business partner, and the corresponding Call Parameters (tsclm0100m000) parameter.

The Call Management module uses response times in the following way:

When you register a call, ERP LN allocates a response time to the call by the following search path:

1. If the call's cluster, or item, is covered by a service contract, the call's response time is the response time defined for the service contract.
2. If no service contract is defined for the call (or no response time defined for the service contract), ERP LN allocates the response time code defined for the call's sold-to business partner.
3. If no response time code is defined for the call's sold-to business partner, ERP LN allocates the response time code defined in the Call Parameters (tsclm0100m000) session.

ERP LN calculates the various response time of a call as follows:

- Reaction time = registration time + response period
 - Solution start time = registration time + solution start period
 - Solution finish time = registration time + solution finish period
-

Note

- If the **Use Priorities in Calculating Times** check box is selected in the **Call Parameters (tsclm0100m000)** session, any priority defined for a call will affect (decrease) the response time, solution start time, and solution finish time.
- ERP LN uses the call's solution times to determine the call priority. For details, refer to Call priority.

Assign and reassign call

You can assign calls to a service center or to a support engineer. In the **Assign Calls to Support Engineer (tsclm1112m000)** session, you can view the calls that are assigned to service centers and assign these calls to support engineers. Particular call details, such as the configuration and the priorities, appear in this session. All the calls that are assigned to a specific service center, and that are not yet assigned to a support engineer, appear in this session. If both the service center and the support engineer are allocated, the call status changes to Assigned.

Use the **Assign a Call (tsclm1113s000)** session to assign a call to a specific service center. You can also specify the support engineer in this session. If the call is assigned to the service center and service engineer, the status of the call changes from Registered to Assigned.

Use the **Assign Calls to Support Engineer (tsclm1114m000)** session to assign a call to a specific support engineer. To assist you in this process, the session lists call details such as the configuration, required activity, and priorities. If both the service center and the support engineer are allocated, the call status changes to Assigned.

Reassign Call

If a call cannot be resolved, the call is reassigned. You can reassign the call to another service center or another support engineer. Most organizations choose to reassign the call before sending out a service engineer. This practice saves the organization time, and saves the customer money. You can reassign calls between service centers from the **Calls (tsclm1100s000)** session, or from the **Reassign Calls between Service Centers (tsclm1215m000)** session, in which you can change calls based on a range of factors.

Use the **Reassign Calls between Service Centers (tsclm1215m000)** session to reassign a range of calls to another service center. The status of the call before transfer must be **Registered**, **Assigned**, or **In Process**. The resulting status of the call depends on the number of employees at the reassigned service center:

- For calls with only one employee, the status change to **Assigned**.
- For calls with multiple employees, the status changes to **Registered**.

Use the **Reassign Calls to Support Engineer (tsclm1220m000)** session to reassign a range of calls to another support engineer. This engineer can work for another service center. The status of the call before transfer must be Assigned or In Process. After transfer, the call status changes to Assigned.

Diagnostic tree construction

A diagnostic tree is an important function in the Call Management (CLM) module and is an information structure that contains a set of questions, along with their expected answers (of which there can be more than one), that is used to help you solve problems. The expected problem and the expected solution can be attached to an answer. A follow-up question can also be attached, which is used to elicit more details before indicating what the expected problem and solution are. You can also specify an item related to the answer, which enables you to switch to the diagnostic tree of the related item, and search the diagnostic tree's path for a solution.

To construct a diagnostic tree

This feature enables you to analyze registered problem calls in a structured way. Diagnostic trees help calltakers to analyze malfunctions or problems, solve the problems remotely, and prevent unnecessary site visits. ERP LN determines the diagnostic tree to be used, based on the registered object or model. To use the diagnosis, you must set up the structure.

Priorities

Call priority is determined by the available time to solve the call, or the available time to start to solve the call, depending on the **Use Priorities in Calculating Times** setting in the Call Parameters (tsclm0100s000) session.

The time left to solve a call and the response time determine the call priority.

In ERP LN, you can assign a priority to:

- Cluster: In the Clusters (tsbsc1100m000) session
 - Serialized item: In the Serialized Items (tscfg2100m000) session
 - Business partner: In the Sold-to Business Partners (tccom4110s000) session
 - Problem: In the Call (tsclm1100m000) session
 - Bad fix: In the Call Parameters (tsclm0100m000) session.
-

In the Call Management module, if a call has any of these priorities assigned, and if the **Use Priorities in Calculating Times** check box is selected in the Call Parameters (tsclm0100m000) session, the call's response times are affected in the following way:

Priority Factor

From each priority, you can calculate a priority factor by the following equation:

`priority factor = priority / 100`

Example

`cluster priority factor = cluster priority / 100`

The call's priority factor

To determine the call's priority factor, multiply all priorities as follows:

`call priority = (cluster priority / 100) or (serialized item priority / 100) * (BP priority / 100) * (problem priority / 100) * (bad fix priority / 100)`

Note

- A priority of zero (0) signifies that the particular priority is irrelevant and left out of the equation.
- The bad fix priority is only used if the call is considered a bad fix.

The reaction time and solution time

The call's priority factor and response time data determine the reaction and solution times for the call by the following formulae:

`reaction time = reported time + (reaction period * priority factor)`

`solution start time = reported time + (solution start period * priority factor)`

`solution finish time = reported time + (solution finish period * priority factor)`

Example

A call is registered at 10 AM on Wednesday. The solution coverage calendar is 9 PM to 5 PM Monday through Friday. The solution start period (of the call's response time) is 21 hours, and the following priorities are defined for the call:

- Problem priority = 50
-

- Item priority = 80

The total priority factor is: $(50/100) \times (80/100) = 0.5 \times 0.8 = 0.40$

The solution start time, therefore, is: 10 am + $(21 \times 0.40) = 10 \text{ am} + 8.4 \text{ hours}$

As a result, the solution to the call's problem must be started no later than 10:24 AM on Thursday.

Escalated and deferred calls

Escalated calls

The term *escalated calls* refers to all calls that must be processed to avoid escalation. This concept of escalated calls enables you to list the calls in order of their actual escalation priority. Escalated calls are neither special, nor are the calls escalated for a specific reason.

Escalated calls are calls that must be dealt with, remain to be assigned, or for which the assigned person is yet to handle the call in process. Blocked calls and waiting calls cannot be defined as escalated calls, because these calls cannot be handled.

Therefore, a call is escalated if the call is:

- **Registered**
- **Assigned**
- **Not blocked**
- **Not waiting**

Escalated calls are listed in order of priority, which is determined by the available time to solve the call, or the available time to start to solve the call, which depends on the **Priority Definition** parameter defined in the Call Parameters (tsclm0100m000) session.

Deferred calls

Deferred calls are calls that must be handled, and for which the status does not change within the specified period. A registered call, for example, is not set to **Assigned** status in time or an assigned call is not set to **In Process** status in time. The **Time Fence** parameter in the Call Parameters (tsclm0100m000) session determines the period for status change.

The time fence is used in two ways:

- The time fence added to the time at which the call is registered indicates when the call must be assigned.
 - The time fence added to the time at which the call is assigned indicates when the call must be in process.
-

In other words, a call is deferred if:

- The call is registered and the current time is past the registration time plus time fence.
- The call is assigned and the current time is past the assigned time plus time fence. The call is not blocked.

Note

In contrast to escalated calls, deferred calls also include waiting calls, because calls that are waiting and have passed the time fence must be brought to the attention of the help desk employee.

To view escalated calls and deferred calls

You can activate a filter through which you can list both escalated and the deferred calls. However, if you have ten escalated calls and ten deferred calls, this does not imply that the list consists of twenty calls, because calls can be escalated and deferred at a given time. This condition applies to calls that have passed the time fence and that are not **Waiting**.

Note

- When a call is blocked, the call is not listed by any of the three possible filters for further processing, because a blocked call is not the responsibility of the help desk. A call is blocked for financial causes, and must, therefore, be addressed by someone other than the help desk manager.
- You cannot view a call that is overdue. However, overdue calls that have not been processed are also deferred calls. In other words, the **Deferred Calls** filter enables you to list the subset of the overdue calls. Similarly, you can use the **Escalated Calls** filter to list calls that are overdue, deferred, and not waiting.

To create a physical breakdown from a Bill of Materials

You can use the **Create Physical Breakdown Structure (tscfg2210m000)** session to create the physical breakdown from a Bill of Material (BOM).

If you create a physical breakdown from a bill of material, this results in a direct copy of effective items present in the Bill of Material (tibom1110m000) session of ERP LN Manufacturing to the **Serialized Items (tscfg2100m000)** session of ERP LN Service. If no item service data is present, ERP LN uses the item service defaults maintained for item type and item group to create items in Service.

To create a physical breakdown from a Bill of Materials

1. Start the **Create Physical Breakdown Structure (tscfg2210m000)** session.
2. In the **Source** field, select **Bill of Material**.
3. Use the **Sales Deliveries** option to create a physical breakdown from Sales (after sales). The end item of the sales order, the production BOM is copied to a physical breakdown. If you select this check box, you can use the fields in the **Selection Range** group box to create a physical breakdown from a range of clusters, items, or serialized items. For this selection range, a physical breakdown is created.
4. If you select the **Item Effectiveness** check box, the items' validity is checked before the items are copied to physical breakdown.

ERP LN validates the following:

If the item is revision controlled and derived from sales deliveries, ERP LN checks for revision from the sales order line. ERP LN checks for the effective date from engineering items for the given item and revision.

If the item is not revision controlled and derived from sales deliveries, ERP LN checks for the effective date from sales based on the **Configuration Date in Sales** field.

If the item is not from sales deliveries then, ERP LN takes the effective date given as input.

- **Unit Effectivity:** When ERP LN creates the physical breakdown structure from a Bill of Material (BOM), ERP LN considers unit effectivity as a validation. The items that belong to the unit effectivity are only created in service. Unit effectivity is checked from the serialized item. If unit effectivity is not present in the serialized item, ERP LN checks the unit effectivity from a sales order line if the item originates from sales.
- **Fall Back on BOM if source is not found:** If you select this check box when you create the physical breakdown structure from an as-built structure or item breakdown and no source item is found, ERP LN copies the bill of material of that item to the physical breakdown structure.
- **Consistency checks:** If the physical breakdown is generated directly from a production BOM, ERP LN performs a consistency check, both at ERP LN **Manufacturing** and ERP LN **Service**, to ensure the structure is defined without any mismatch. The items in such a structure must be defined in ERP LN Service with appropriate service-item data with related configuration control, and checked for consistency.

ERP LN performs the following consistency checks:

To distinguish between the items relevant and not relevant to service, ERP LN copies the configuration-controlled items, namely serialized or anonymous items, into physical breakdown. If no service-item data is available for an item,

based on service defaults, the item data will be created in items service and copied to physical breakdown.

Note

You must create service item data for all the items copied from a production bill of material to the physical breakdown structure.

ERP LN checks for consistency with respect to the structure formation. A serialized item must always be situated above an anonymous item to ensure that the structure remains consistent with the item definition. ERP LN begins to copy when inconsistency is detected in the structure formation and an error report is generated.

ERP LN prints an error report if a serialized item is present under an anonymous item, as illustrated in the following example:

Example

Level	Item	Conf. Cont.	Item Service Data Present
0	X	Serialized	Yes
1	Y	Anonymous	Yes
2	A	Serialized	Yes ----- Problem 1
2	B	None	No
1	Z	Anonymous	Yes
2	A	Serialized	Yes ----- Problem 2
3	B	None	No
4	C	Anonymous	Yes ----- Problem 3

All three problems are caused by serialized items present under anonymous items.

ERP LN prints the following error report:

No PBD was generated for item X for the following reasons:

- Parent item (Y-anonymous) has a lower configuration control setup than Child item (A-serialized).
- Parent item (Z-anonymous) has a lower configuration control setup than Child item (A-serialized).
- Parent item (B-none) has a lower configuration control setup than Child item (C-anonymous).

ERP LN checks for consistency with respect to the loops in the bill of material (BOM). If two anonymous items occur in an opposite fashion, with respect to an existing structure definition, the anonymous items can subsequently end up in a loop.

ERP LN detects a loop in a bill of material, ERP LN prints an error report, as illustrated in the following example:

Example

Level	Item	Conf. Cont.	Item Service Data Present
0	X	Serialized	Yes
1	Y	Serialized	Yes
2	A	Serialized	Yes
2	B	Serialized	Yes
1	Z	Serialized	Yes
2	A	Serialized	Yes
3	B	Serialized	Yes
4	X	Serialized	Yes ----- Problem 1

ERP LN prints the following error report:

For item X, no PBD could be generated for the following reasons:

- Cycle detected in BOM.

Call Status

The call status helps you to keep track of a call and to determine the next action. The sequence of the call status is strictly regulated. The call status is checked before a step is carried out. After you perform particular steps, the status is updated automatically.

If, for example, you add a new call, the call's status will be **Registered**. The status changes as follow-up activities occur.

ERP LN uses the status to determine the following:

- At what stage of the call handling process a support engineer is working on the problem
- Whether a service engineer is required
- Whether the business partner has accepted the actual solution provided

A call can have the following statuses:

- **Registered:** The call taker has registered the call.
 - **Assigned:** The call has been assigned to a service engineer.
 - **In Process:** The service engineer has started to solve the call.
 - **Solved:** The service engineer has solved the call.
 - **Transferred:** The call has been transferred from Call Management to Service Order Control.
 - **Accepted:** The customer has accepted the solution provided.
-

To set up Master Data for Call Management

The call handling process uses data defined in **Call Management** data setup throughout the life cycle of the call. Call Management master data enables you to define the fixed data, such as response times, call groups, priority time scales, invoicing intervals, and specific call parameters.

To set up master data

To set up **Call Management master data**, take the following steps:

1. Define the call parameters.
In the **Call Parameters (tsclm0100m000)** session, you can set parameters to do the following:
 - Delete the transaction log after accepting a call.
 - Match service order numbers. When you generate a service order for a call, the service order number matches the call number from which the service order is generated.
 - Match maintenance sales order numbers. If you generate a maintenance sales order for a call, the maintenance order number matches the call number from which the order number is generated.
 - Define the invoice intervals and coverage types.
 - Define response time for all calls in the **Call Management** module that are not covered under any contract, or whose sold-to business partner does not have a default response time.
 - Indicate whether the solution start period or the solution finish period must be considered in time calculations at the service-order level. You can also use this setting to calculate the actual time left to solve a call.
 - Use priorities with the call response times to calculate reaction times, solution start times, and solution finish times.

- Signal and block calls if the credit limit is exceeded, if the credit review is overdue, if the invoice is overdue, or if the business partner is doubtful of invoice-to business partner.
 - Notify the user of the existing calls for the sold-to business partner, cluster, or serialized item. When you register a new call, ERP LN notifies the user of the calls registered previously for the sold-to business partner, cluster, or serialized item.
2. Use the **Response Times (tsclm0120m000)** session to maintain response times. The **Call Management** module uses response times in the following way:
- When you register a call, ERP LN allocates a response time to the call by the following search criteria:
- If the cluster or item defined for the call is covered by a service contract, the call's response time is the response time defined for the service contract.
 - If no service contract is defined for the call, or if no response time is defined for the service contract, ERP LN allocates the response time code defined for the call's sold-to business partner.
 - If no response time code is defined for the call's sold-to business partner, ERP LN allocates the response time code defined in the **Call Parameters (tsclm0100m000)** session.
3. Use the **Priority Time Scale (tsclm0124m000)** session to specify a range of time periods. ERP LN uses these time periods to determine the initial priority and the actual priority of a call in the **Call (tsclm1100m000)** session. The priority of a call is determined by the specified time period in which the call's initial time to solution and actual time to solution fall.
4. Use the **Call Groups (tsclm0150m000)** session to view and define call groups.
5. Use the **Invoicing Intervals (tsclm0170m000)** session to define and maintain invoicing intervals. Time intervals for invoicing are used in **Service** to determine which proportion, if any, of time that is spent resolving calls is finally invoiced to the business partner.
-

Chapter 4

Call Management Procedures

4

This chapter provides a detailed explanation about the Call Handling processes.

Call handling

The call handling process consists of the following steps, each of which is described subsequently:

1. The call taker registers the call. ERP LN then changes the call status to **Registered**.
2. The call taker assigns the call to a support engineer, if the call taker and the support engineer are not the same person. ERP LN changes the call status to **Assigned**
3. The support engineer starts to process the call. ERP LN changes the call status to **In Process**
4. The support engineer analyses and solves the problem, and sets the status of the call to **Solved**.
5. If the support engineer is unable to solve the problem, the call can be reassigned to another support department or support engineer.
6. If the customer accept the provided solution and the call taker or the support engineer sets the call status to **Accepted**.

1. **Register the call**

Enter the details of the customer, item, and the problem in the Call (tsclm1100m000) session.

If any of the blocking reasons selected in the **Call Parameters (tsclm0100m000)** session apply to the customer, ERP LN displays a message. If registration of the call is blocked, the call taker must inform the customer of the blocking reason so that the customer can resolve the blocking reason.

After you register the call details, ERP LN sets the call status to **Registered**.

If you also act as the support engineer, process the call as described in Step 5.

2. Assign the call

Use the **Calls to be Assigned (tsclm1513m000)** session to assign the call. Based on the priority of the call, assign the calls to a support engineer to solve or to a service engineer if the call is an emergency call. Transfer the call to the field service engineer if the problem must be addressed in the field.

If you allocate both the service center and the support engineer, ERP LN sets the call status to **Assigned**.

3. Process the call

Set the call status to **In Process** when you start to investigate the call. Before you attempt to solve the call, you can set the timer ton **On**.

To identify the problem, in some cases, you must contact the customer and ask further questions. If this takes some time, you can set the call status to **Waiting** to indicate that more information is required from the business partner.

4. Solve the call

After you solve the problem, ERP LN sets the call status to **Solved**. Before ERP LN sets the call status to solved, enter the value in **Actual Problem, Actual Solution, Time Spent to solve the call** in Call (tsclm1100m000) session.

5. Deliver the solution

Set the call status to **Accepted** if the customer is satisfied with the solution the call center provides.

If the support engineer cannot solve the call, or if the call center cannot handle the type of call, you can reassign the call or transfer the call to a different department.

To reassign the call

If the support engineer cannot solve the call, you can reassign the call to a different support department or a different support engineer.

To reassign calls, use one of the following sessions:

- Reassign Calls between Support Departments (tsclm1215m000)
- Reassign Calls between Support Engineers (tsclm1220m000)

To transfer the call to Service Order Control

- If a field service activity is required, you can transfer the call to Service Order Control, or immediately plan the work in Service Order Control if the visit is urgent.
-

- To transfer a call to Service Order Control, in the Call (tsclm1100m000) session, on the **Transfer to Service Order** menu, click **Transfer to Service Order**. ERP LN changes the call status from **In Process** to **Transferred**.

To transfer a call to subcontractor

- If the item is covered by a subcontract agreement, ERP LN displays the subcontract agreement information when you register the call.
- Depending on the status specified in the subcontract agreement, you can decide to transfer the call to the subcontractor.
- To transfer a call to a subcontractor, in the Call (tsclm1100m000) session, on the **Transfer to Service Order** menu, click **Transfer Call to Subcontractor**.

To transfer a call to Maintenance Sales Order Control

In some situations, you can transfer the call to Maintenance Sales Order Control.

A maintenance sales order is required in some of the following situations:

- The customer needs some spare parts and calls the call center with this request.
- The customer has a problem with the items and wants to send the items to the depot for repair. The customer requires a replacement item or loan item to use and return after receiving the repaired original item.

To transfer a call to Maintenance Sales Control, in the Call (tsclm1100m000) session, on the **Transfer to Service Order** menu, click **Transfer to Maint. Sales Order**.

To create the maintenance sales orders, use any of the following options:

- **For Repair in Depot**
- **For Parts Delivery**
- **For Parts Receipt**
- **For Parts Loan**

Register call

The process to register a call includes the following activities:

- Define a call.
 - Find the best response periods and invoice interval.
 - Determine the priority of the call.
 - Calculate various dates and times.
-

- Check the blocking reasons for the call if any.

Use the **Call (tsclm1100m000)** session to register new calls and to process call details, which include general data, business partner data, routing data, and diagnosis data.

To register a call, run the **Call (tsclm1100m000)** session and enter the following details:

1. Enter the sold-to business partner. If you register a new call, ERP LN notifies you of the calls registered previously for the specific sold-to business partner, cluster, or serialized item. ERP LN specifies the calls that are completed, in process, or registered by other call takers with the customer. To control the search for existing calls, you can set the **Search Based On** and **Show Message if There Are Existing Calls** parameters in the **Call Parameter (tsclm0100m000)** session.
 2. ERP LN checks for blocking of the sold-to BP on the basis of blocking parameter set in the **Call Parameter (tsclm0100m000)** session.
 3. Enter the cluster for which the call is raised.
 4. Enter the item code for which the call is registered.
 5. Enter the serial number of the item for which the call is raised. You can select this serial number from the **Serialized Items (tscfg2100m000)** session, which includes other details such as the item code and description, cluster, business partner, and item grouping. *You can only select a serialized item of the selected cluster.*
 6. If the call solving costs are covered by a service contract or warranty, ERP LN displays a message to inform you.
 7. In the **Description** field, enter a brief description of the problem reported by the customer. You can add further details in the **Comment** field.
 8. In the **Reported Problem** field, you can enter a problem code. If the symptoms are caused by a known, defined problem, you can select the problem from the **Problems (tsclm3130m000)** session.
 9. Enter the call group. You can define call groups in the **Call Group (tsclm0150m000)** session.
 10. You can select the **Emergency** check box and/or the **Bad Fix** check box, as applicable.
 11. Enter the invoice details, such as the invoice-to business partner and the invoice interval. ERP LN fetches the invoice interval defined for the sold-to business partner in the **Parameter (tsclm0100m000)** session or you can select the invoice interval in the **Invoice Intervals (tsclm0170m000)** session.
 12. If the call is transferred to **Service Order Control**, you must enter the support department and the support engineer details.
 13. Click **Save** to register the call. ERP LN generates a call number for the registered call and changes the call status to **Registered**.
-

Transfer call

You can transfer a call, for example, for the following reasons:

- **The call requires field engineer service**
The calltaker enters the details of the service department to which the call must be transferred and generates a service order to transfer the call to the service order control.
- **The call must be handled by a subcontractor**
If the call center signed a contract with a subcontractor to provide service to the given item, the calltaker views the details of the subcontract agreement and informs the subcontractor of the call details, such as the item, location address, and the problem, either by phone, fax, or e-mail.
- **The call requires depot repair or shop maintenance**
The calltaker transfers the call to the maintenance sales control in which a maintenance sales order is created with the details of the call.

The following section describes each of these steps in detail.

To transfer a call to Service Order Control

To transfer a call to Service Order Control, take the following steps:

1. Register the call in the **Call (tsclm1100m000)** session. Check if the call must be transferred to service order control. If a service engineer is required, you can transfer the call to Service Order Control, or immediately plan the work in Service Order Control.
2. If the call must be transferred to service order control, in the **Call (tsclm1100m000)** session, on the **Routing** tab, enter **Service Department**.
3. If the call is marked as an emergency, specify a value in the **Service Engineer** field on the **Routing** tab in the **Call (tsclm1100m000)** session.
4. Transfer the call to service order control: in the **Call (tsclm1100m000)** session, on **Specific** menu, click **Transfer to Service Order** to transfer the call to Service Order Control.
5. If you transfer a call to service order control, ERP LN changes the call status from **In Process** to **Transferred**.

To transfer a call to Maintenance Sales Order Control

To transfer a call to Maintenance Sales Order Control, take the following steps:

1. Register the call in the **Call (tsclm1100m000)** session.
 2. Check if the call must be transferred to Maintenance Sales Order Control. A maintenance sales order is required in the following cases:
-

- The customer needs spare parts and calls the call center to meet the request.
 - The customer has a problem with the items and wants to send the items to the depot for repair. The customer requires a replacement item or loan item to use and return after they receive the repaired original item.
3. In the **Call (tsclm1100m000)** session, on the **Routing** tab, enter the **Service Engineer** and the **Repair Department**.
 4. To transfer the call to Maintenance Sales Order Control, in the **Call (tsclm1100m000)** session, on the **Specific** menu, click **Transfer to Maintenance Sales Order Control**.
 5. ERP LN changes the call status from **In Process** to **Transferred**.
 6. To create the maintenance sales orders, you can use any of the following lines:
 - **For Repair in Depot**
 - **For Parts Delivery**
 - **For Parts Receipt**
 - **For Parts Loan**

To transfer a call to Subcontractor

To transfer a call to Subcontractor, take the following steps:

1. Register the call in **Call (tsclm1100m000)** session.
2. Check if the call must be transferred to subcontractor. If the item is covered by a subcontract agreement, ERP LN displays the subcontract agreement information when you register the call.
3. To transfer a call to a subcontractor, in the **Call (tsclm1100m000)** session, on the **Specific** menu, click **Transfer Call to Subcontractor**. When you transfer the call to the subcontractor, ERP LN prompts you to identify the media through which the information must be passed to the subcontractor.
4. If you transfer a call to a subcontractor, ERP LN changes the call status from **In Process** to **Transferred**.

Depending on the status specified in the subcontract agreement, you can decide to transfer the call to the subcontractor.

Solve the call

To solve the call, you can provide the actual problem identified, the actual solution determined, and actual activity required. Based on the time spent to solve the call, and based on whether the company invoices the customer, the total costs and sales incurred on the call is determined.

The process to solve a call consists of the following steps:

1. Register the call in the **Call (tsclm1100m000)** session. The calltaker tries to identify the problem and the required solution through questions and answers from the customer. You can use the **Diagnostic Tree (tsclm3120m000)** session to construct, maintain, and use diagnostic trees to solve calls.
2. Solve the call. If the call is solved through help desk, the support engineer can set the call status to Solved. In the **Call (tsclm1100m000)** session, on the **Specific** menu, click **Solve** to solve a call.
3. If the support engineer is unable to solve the call, you can reassign the call to another support engineer or support department. To reassign multiple calls, use the Reassign Calls between Support Departments (tsclm1215m000) session and the Reassign Calls between Support Engineers (tsclm1220m000) session.
4. Record the time spent on the call. To record the time spent, you can either set the timer or enter the time manually. If the support engineer keeps the call in waiting, ERP LN updates the used time. When the support engineer solves the call and stops the timer, the spent time is updated.
5. ERP LN updates the **Calls - History (tsclm8520m000)** session.

If the customer accepts the solution the support engineer provides, you must change the call status from **Solved** to **Accepted**.

Call invoicing

You can use **Central Invoicing** to invoice the business partner for the service calls that you handle.

Invoicing parameters

Before you invoice a call, you must first set the invoicing parameters in the Call Parameters (tsclm0100m000) session:

- **Invoice after Call**
Select this check box to enable call invoicing.
- **Time Interval**
When a call is logged, the person who handles the call must determine the invoice interval for the customer. If the sold-to business partner has signed a contract, the invoice interval is taken from the service contract (help desk) terms. If the sold-to business partner did not sign a contract, the invoice interval of the call center, which you define here, is used.

The time interval for invoicing is used to check if the time spent on the call is invoiceable or not based on the invoice interval limits.

Start the Invoicing Intervals (tsclm0170m000) session to define a time interval. The main characteristics of the time interval are the lower and upper limits, which are used to determine whether the time spent on a call is invoiced. If the time spent is less than the lower limit, no invoice is created. Otherwise, the actual amount of time spent is invoiced, with the upper limit as maximum.

- **Cost Component**

The default cost component that is used to invoice a call, and which can also be used to influence the level of contract or warranty coverage. Run the Cost Components (tcmcs0148m000) session to select or define the appropriate cost component.

- **Coverage Type**

The value in this field indicates to what extent work is covered under warranty, and what part of the activities can be charged. To select the appropriate coverage type, start the Coverage Types (tsmdm0135m000) session.

- **Path for Labor Rate**

Specify up to three levels for the search path used to retrieve the labor rate:

- **Cluster**
- **Support Engineer**
- **Activity Taken**
- **Serialized Item Group**
- **Support Department**

Invoicing a call

The call invoicing procedure consists of the following steps:

1. Select the call in the **Call to Be Invoiced (tsclm1519m000)** session.
 2. On the **Specific** menu, click **(Create) Invoice**. The **Call Invoicing (tsclm1105s000)** session starts, in which you can view the call invoicing details.
 3. In the **Call Invoicing (tsclm1105s000)** session, on the **Specific** menu, click **Print Draft invoice** to print a draft invoice, which you can check.
 4. In the **Call Invoicing (tsclm1105s000)** session, on the **Specific** menu, click **Create Invoice** to transfer the call invoicing details to **Central Invoicing**.
 5. For details about the invoicing procedure, refer to Invoicing.
-

Call diagnostics

An important function in the Call Management (CLM) module is the Call diagnostics.

If you register a call, you can enter the problem and the item details. You can then initiate the diagnostic tree specific to the equipment. You can select a potential problem and solution with the help of a diagnostic tree.

To view the diagnostic tree, in the **Call (tsclm1100m000)** session, on the **Specific** menu, click **Diagnostic Tree**. ERP LN determines which diagnostic tree must be used based on the item or serial number.

Before you open the diagnostic tree, you must set up the structure.

To construct a diagnostic tree

To construct a diagnostic tree, take the following steps:

Step 1: Define questions and answers

In the Call Management module, you can maintain lists of questions in the Questions (tsclm3100m000) session, and you can maintain lists of answers in the Answers (tsclm3105m000) session. The questions and answers can be based on previous resolutions of calls.

Step 2: Select a start question

In the Diagnostic Tree (tsclm3120m000) session, in the **Question** field, select a start question from the Questions (tsclm3100m000) session.

Step 3: Define possible answers

You can use the details session to select possible answers (from the Answers (tsclm3105m000) session) for the start question.

Step 4: Define the outcome for a possible answer

For each answer listed, you can define:

- A possible problem: Select the problem from the Problems (tsclm3130m000) session.
- A possible solution: Select a solution from the Solutions (tsclm3135m000) session.
- A follow-up question: Select a question from the Questions (tsclm3100m000) session.
- The item to which the related answer refers: Select the item from the Items - Service (tsmdm2100m000) session.

Step 5: Define problem and solution by each serialized item group

- You can use the **Problems by Serialized Item Groups (tsclm3131m000)** session to view and maintain problems by serialized item group.
- You can use the **Solutions by Serialized Item Groups (tsclm3136m000)** session to view and maintain solutions by serialized item group.

Step 6: Probability Analysis - Problems and Solutions

In the **Probability Analysis - Problems and Solutions (tsclm3161m000)** session, you can determine the probability of the selected solution to solve the problem. If the probability of selected solution is low, you can select another combination from the **Probability Analysis – Problems and Solutions (tsclm3161m000)** session with a high probability. The call will be updated with values you select.

Step 7: Statistics- Problems and Solutions

When a call is solved or a service order activity is completed, data in the **Statistics - Problems and Solutions (tsclm3160m000)** session is updated.

Step 8: Service Resolution - Probability Analysis

The **Service Resolution - Probability Analysis (tsclm3150m000)** session is updated when:

- A call is solved and the relevant details are added.
 - A service order activity is created, either from a call or manually. This history data is updated when you update the activity.
-

Appendix A

Glossary

A

as-built structure

The actually built structure of a product including the serial numbers.

bad fix

A call from the same customer about a previously solved problem regarding the same item.

bill of material (BOM)

A list of all parts, raw materials, and subassemblies that go into a manufactured item and show the quantity of each of the parts required to make the item. The BOM shows the single-level product structure of a manufactured item.

cluster

A set of serialized items that have the same location and are owned by the same business partner. Grouping serialized items into a cluster enables you to maintain them collectively.

cost component

A cost component is a user-defined category for the classification of costs.

Cost components have the following functions:

- To break down an item's cost price, sales price, or valuation price.
- To create a comparison between the estimated production order costs and the actual production order costs.
- To calculate production variances.
- To view the distribution of your costs over the various cost components in the Cost Accounting module.

Cost components can be of the following cost types:

- **Material Costs**
- **Operation Costs**
- **Surcharge on Material Costs**
- **Surcharge on Operation Costs**
- **WIP Transfer Costs**
- **General Costs**

Note

If you use Assembly Control (ASC), you cannot use cost components of the **General Costs** type.

item

A standard maintenance item.

item breakdown

A standard item's list of constituent components. The item breakdown can be displayed as a multilevel structure or as a single-level structure, and can be used as input for a physical breakdown.

maintenance sales order

Orders that are used to plan, carry out, and control the maintenance on customer-owned components, products and the logistic handling of spare parts.

physical breakdown

A serialized item's composition and structure, defined by the parent-child relationships of its constituent items. The physical breakdown can be displayed in a multilevel structure or a single-level structure.

production BOM

An alternative term for the bill of material and is used to distinguish the Production BOM from the Engineering BOM.

response time

A response time defines, from the time a call is registered, the period of time within which: The service provider must react to the call; A solution to the call's problem must be started; A solution to the call's problem must be finished.

serialized item

An item that is uniquely identified by the item code (manufacturer part number) in combination with the serial number.

service-item data

Information about the service item.

Index

as-built structure, A-1
Assign and Reassign Call, 2-4
bad fix, A-1
bill of material (BOM), A-1
Call diagnostics, 5-1
Call Handling, 4-1
Call handling concepts, 2-1
call invoicing, 4-7
Call Status, 2-12
cluster, A-1
Configuration Management, 2-8
cost component, A-2
deferred, 2-7
Diagnostic tree, 2-5
escalated, 2-7
invoice, calls, 4-7
item, A-2
item breakdown, A-2
maintenance sales order, A-2
Master Data, 3-1
physical breakdown, A-2
Priorities, 2-5
production BOM, A-3
Register Call, 4-3
response time, 2-3, A-3
serialized item, A-3
service-item data, A-3
Solve Call, 4-6
Transfer Call, 4-5
